

VALIDATION PLATFORM CREDENTIALS

Security Validation comes with a set of default credentials, which include one-use passwords that must be changed the first time you login. Below you'll find the default credentials for all form factors of the Security Validation components, as well as instructions on how to change the password.

Password Settings

The platform has minimum password requirements. The admin can modify these, but by default, they are:

- Minimum length: 8
- Numerical characters required: 2
- Special characters required: 2
- Requires upper and lower case characters

Actor Console Credentials

Form Factor	Username	Credential Type	Password
OVA, VHD	nodeone	password	pc4p5RFUN!?
Installable software	Managed by underlying OS		
AMI	centos (4.13.0.0 and earlier)	Key	
	rocky (4.14.0.0 and later)		

Protected Theater Console Credentials

Form Factor	Username	Credential Type	Password
OVA, VHD	nodeone	password	pc4p5RFUN!?

Changing Console Credentials - OVA & VHD Form Factors

The first time you SSH to the console, you are prompted to change the password. If you need to change the password at a later time, use the following process.

1. Connect via command line.

```
ssh nodeone@<ip>
```

2. Process the following command, using the username for the account to be changed:

```
sudo passwd nodeone
```

Director UI Credentials

Username	Password
admin@verodin.com	pc4p5RFUN!?

Change the password for the admin@verodin.com account

The first time you log in, you are prompted to change the password.



If you are using this account, the following process is how you change the password for the account. Otherwise, use [Manage User Accounts \(https://docs.mandiant.com/home/msv-managing-user-accounts\)](https://docs.mandiant.com/home/msv-managing-user-accounts).

1. Launch the Director.
2. Select **User > User Preferences**.
3. For **Current Password**, enter the current password for admin@verodin.com.
4. For **Password** and **Password confirmation**, enter the password you want to use for the admin@verodin.com.
5. Click **Update Account Settings**.

Director Console Credentials

Form Factor	Username	Credential Type	Password
OVA, VHD	nodeone	password	pc4p5RFUN!?
installable software	Managed by underlying OS		
AMI	centos (4.13.0.0 and earlier) rocky (4.14.0.0 and later)	Key	

Set the Director Database password

The Director Database password is configured for the first time when you install the Director. The same commands are used each time you want to reset the password. Keep in mind the following conditions:

- If your password uses special characters, you must escape those characters
- After changing the password, you must run `vrestart`

If you are uncertain if a character needs to be escaped, run this command first, adding the escapes where you think they are needed. If it comes out as you expect, you've escaped it correctly.



```
echo This!\sMynew\$P@ssw0rd!
```

The results of that command would be:

```
This!\sMynew\$P@ssw0rd!
```

To create or update the Director database password, use the `vsetdb` command:

```
sudo vsetdb --password NEW_PASSWORD  
vrestart
```

Replace `NEW_PASSWORD` with the password you want to use for your Security Validation database.

You can also run the `vsetdb` using this format:

```
sudo vsetdb -p NEW_PASSWORD  
vrestart
```